

Netviewer Admin

Automated software distribution

Netviewer Admin hosts may be installed via centrally controlled software distribution. The setup program can be started with custom parameters.



IMPORTANT:

To install a Netviewer Admin host, you will need local administrator rights on the target computer.

Examples and available parameters are listed below.

General installation call:

```
Netviewer_Admin_Setup.exe [Setup parameter] /v"[Netviewer parameter]"
```

Examples

Example 1: Unsupervised installation

```
Netviewer_Admin_Setup.exe /S /v"PNVLICENSEKEY=xxx /qn"
```

Example 2: Unsupervised installation with host password and proxy

```
Netviewer_Admin_Setup.exe /S /v"PNVLICENSEKEY=xxx PNVUSEHOSTPASSWORD=1  
PNVHOSTPASSWORD=xxx PNVUSEPROXY=1 NVPROXYHOST=gowron PNVPROXYPORT=3128  
/qn"
```

Example 3: Supervised installation in a defined installation path with prompt to enter host password

```
Netviewer_Admin_Setup.exe /v"PNVLICENSEKEY=xxx PNVUSEHOSTPASSWORD=1  
INSTALLDIR=c:\admin_6"
```

Applicable parameters

Setup parameter	Description
/S	Setup's language selection dialog will not be displayed during installation.
/v	Netviewer-specific installation parameters follow this parameter.

Netviewer installation parameter	Text displayed in the program interface
INSTALLDIR= <i>(DEFAULT= %PROGRAMFILES%\Netviewer Admin\)</i>	Define installation directory
PNVLICENSEKEY=xxx	License key
PNVUSEHOSTPASSWORD=0 <i>(DEFAULT)</i>	Do not use host password
PNVUSEHOSTPASSWORD=1	Use host password
PNVHOSTPASSWORD=passwordexample	Host password
PNVUSEPROXY=0 <i>(DEFAULT)</i>	Use automatic proxy settings
PNVUSEPROXY=1	Use the following proxy server connection data
PNVPROXYHOST=proxy.host.exampleaddress	Address
PNVPROXYPORT=exampleportnumber	Port
PNVPROXYAUTH=0 <i>(DEFAULT)</i>	No authentication
PNVPROXYAUTH=1	Proxy authentication
PNVPROXYUSERNAME=exampleusername	Username
PNVPROXYPASSWORD=examplepassword	Password
PNVPROXYAUTH=2	Integrated Windows authentication
PNVPROXYDOMAIN=exampledomain	Domain
PNVPROXYUSERNAME=exampleusername	Username
PNVPROXYPASSWORD=examplepassword	Password

Netviewer installation parameter	Description
PNVHOSTALIAS=examplealias	Assign an alias to the host.
PNVINICIALCVTREE=examplefoldername	Assign the host to an existing folder in the computer manager.
/qn	MSI installation dialogs will not be shown during installation



Note:

If you start installation without the /S and /qn parameters, the Netviewer installation parameters will be initialized in the installation dialogs with these values.